


DumpExam

CONTACT | MY CART (5) 



HOME ▾ CERTIFICATIONS ▾ ABOUT ▾ HOW TO PAY? ▾ GUARANTEE ▾ FAQ ▾



Try before you buy

Download a free sample of any of our exam questions and answers

24/7 customer support, Secure shopping site

Free One year updates to match real exam scenarios

If you failed your exam after buying our products we will refund the full amount back to you.

Select a vendor... ▾

Select an exam... ▾

Your email address

 Free Download

Over **28965+** Satisfied Customers

 About Us

QUALITY AND VALUE

DumpExam Practice Exams are written to the highest standards of technical accuracy, using only certified subject matter experts and published authors for development - no all dumps.

TESTED AND APPROVED

We are committed to the process of vendor and third party approvals. We believe professionals and executives alike deserve the confidence of quality coverage these authorizations provide.

EASY TO PASS

If you prepare for the exams using our DumpExam testing engine, It is easy to succeed for all certifications in the first attempt. You don't have to deal with all dumps or any free torrent / rapidshare all stuff.

TRY BEFORE BUY

DumpExam offers free demo of each product. You can check out the interface, question quality and usability of our practice exams before you decide to buy.



<http://www.dumpexam.com>

The best exam dump, valid dumps PDF, accurate exam materials provider

Exam : **700-070**

Title : Cisco TelePresence IX5000
Series Immersive Solutions

Vendor : Cisco

Version : DEMO

NO.1 How many presentations can be shared in a direct IX5000-to-IX5000 call?

- A. two
- B. three
- C. four
- D. one

Answer: A

Explanation:

On an IX-to-IX point-to-point conference, you can share up to two presentation streams - for example, one presentation content source and one whiteboard source. If hosting a meeting locally with no videoconferencing, you can share up to three presentation streams.

Reference:

http://www.cisco.com/c/en/us/td/docs/telepresence/ix_sw/8_x/admin/guide/ix_8_admin_guide/ix_sw_features.html

NO.2 How can you change presentation display options during a call?

- A. Open the share tray and drag the presentation to the desired location.
- B. Open the share tray and assign display numbers to each presentation.
- C. Open the system settings and reconfigure the display options.
- D. Open the participant list and drag the presentation to the desired location.

Answer: A

Explanation:

The share tray allows you to move and duplicate content to and from the main and presentation displays.

To show the share tray, tap Share.

To add content to the conference, drag the content from the share tray to the presentation area.

To remove content from the conference, drag the content from the presentation area to the share tray.

Reference: http://www.cisco.com/c/dam/en/us/td/docs/telepresence/ix_sw/8_x/user/guide/ix-8-1ug.pdf

NO.3 Which step is required during pre-installation of the IX5000?

- A. Hang ceiling lights.
- B. Install wall panels.
- C. Verify that the room floor is level.
- D. Verify that appropriate licenses, upgrades, and tools are available.

Answer: D

NO.4 Where can you find packet-transmission statistics?

- A. Monitoring > Maintenance
- B. Monitoring > Network Data
- C. Monitoring > Statistics
- D. Monitoring > Call Info

Answer: B

Explanation:

Use the Network Data section to view packet transmission statistics collected from the network. Data is listed in columns labeled as if you were looking at the back of the system. For example, on an IX5000, the labels would indicate statistics from the left, center, and right codecs.

To monitor network statistics:

Step 1

In the Monitoring page, scroll down to Network Data. Your network data appears

Reference:

http://www.cisco.com/c/en/us/td/docs/telepresence/ix_sw/8_x/admin/guide/ix_8_admin_guide/ix_sw_mntr.html

NO.5 What is the maximum image resolution of the 4K UHD camera display in the IX5000?

- A. 1080p60
- B. 1280p60
- C. 1080p30
- D. 720p30

Answer: A

Explanation:

Video resolution

Native support up to 1920 x 1080p, 60 fps

Content frame rate

Content sharing up to 1920 x 1080p resolution, 30fps

<http://www.cisco.com/c/en/us/products/collateral/collaboration-endpoints/ix5000-series/datasheetc78-733257.html>